

## Override List Box Data

If you need to change the default values in a list box at run time, it can be done in a non-grid form.

Set up a variable (ldat\_list\$ in the following example) that will contain as many items as you want, with each item containing a 20 character description followed by a tilde (~), followed by the character to be associated with the description, followed by a semicolon. Once the variable is complete, set the table column attribute named LDAT with that variable.

### Example: in BFMC (Before Form Creation)

```
ldat_list$=pad("Customer",20)+"~"+"C;"
if pos(sas01a.customer_lev$="PI")
  ldat_list$=ldat_list$+pad("Product",20)+"~"+"P;"
endif
if pos(sas01a.customer_lev$="I")
  ldat_list$=ldat_list$+pad("Item",20)+"~"+"I;"
endif
callpoint!.setTableColumnAttribute("SAR_CUSTOMER.SA_LEVEL","LDAT",ldat_list$)
```

Note that this **MUST** be done before the form is created or it will not work.